

PROJECT NAME



BEGINNER

WHAT YOU'LL NEED

- Jolly & Joy Chain 50g x 7 balls Main Colour (M) Red; x 3 balls 1st Contrast (C1) Green and Jolly & Joy Tinsel 50g x 1 ball 2nd Contrast (C2) White.
- A 4.50mm crochet hook or size required to give correct tension.
- Scissors, yarn needle, tape measure

Measurements		
SIZE		
Width (approx)	cm	53
Length (approx)	cm	68

TENSION

16 tr and 10 rows to 10cm over treble fabric, using a 4.50mm hook and M.

SACK (MAKE 2 PIECES)

Using 4.50mm hook and M, make 89ch.

1st row - Miss 3ch (counts as 1tr), 1tr in each ch to end. turn ... 87tr.

2nd row - (1dc, 1ch) in first tr (counts as 1tr), 1tr in each tr to end, turn.

2nd row form treble fabric when repeated.

Rep 2nd row 4 times ... 6 rows in all.

Beg Stripe Patt -

Working in stripes of 2 rows C1 and 6 rows M, work a further 54 rows, thus ending with 4 rows of M. turn ... 60 rows in all.

Next row (eyelet row) - (1dc, 1ch) in first tr. * 1ch, miss next tr, 1tr in next tr, rep from * to end, turn.

Next row - (1dc, 1ch) in first tr, * 1tr in next ch sp, 1tr in next tr, rep from * to end.

Fasten off M.

Beg Top Band -Using C2, cont in treble fabric, until band measures 5cm.

Fasten off.

FINISHING

DO NOT PRESS. Using mattress st, join lower and side edges together to form sack, matching stripes. Cut 12 lengths of C2 x 2 metres long. Knot securely together at one end and trim to make a 5cm tassel. Using 4 strands for each section make a plaited cord. Knot securely 10cm from end of cord and trim to form a second 5cm tassel. Thread cord through evelet row and draw up to fasten.

